

# HS-DH500GLメモ

2010年01月12日 03時44分13秒

メモ。

## kernels

```
mv initrd.img to initrd.zip
unzip initrd.zip
  → extract initrd.buffalo
(YvSInIQopeipx66t_DCdfEvfP47qeVPhNhAuSYmA4)
```

## acp\_commander.jar

[http://downloads.buffalo.nas-central.org/TOOLS/ALL\\_LS\\_KB\\_ARM9/ACP\\_COMMANDER/](http://downloads.buffalo.nas-central.org/TOOLS/ALL_LS_KB_ARM9/ACP_COMMANDER/)

2013/02/01 最近の機種はもう少しオプションを付け加えないとダメなので注意

```
F:\acpcommander>java -jar acp_commander.jar -t xxx.xxx.xxx.xxx -o
there seems to be no existing prefs, write default values
ACP_commander out of the nas-central.org (linkstationwiki.net) project.
Used to send ACP-commands to Buffalo linkstation(R) LS-PRO.
WARNING: This is experimental software that might brick your linkstation!
Using random connID value = B9A859BF7526
Using target:  HS-DHGLCA1/xxx.xxx.xxx.xxx
Starting authentication procedure...
Sending Discover packet...
Found:  HS-DHGLCA1 (/xxx.xxx.xxx.xxx)      HS-DHGL(JINMU) (ID=00010)
mac: 00:16:01:xx:xx:xx  Firmware= 1.200      Key=xxxxxxxx
Trying to authenticate EnOneCmd...      ACP_STATE_OK
start telnetd...      OK (ACP_STATE_OK)
Reset root pwd...      Password changed.
You can now telnet to your box as user 'root' providing no / an empty
password.
F:\acpcommander>
```

## telnet

```
$ telnet xxx.xxx.xxx.xxx
Trying xxx.xxx.xxx.xxx...
Connected to xxx.xxx.xxx.xxx.
Escape character is '^]'.
```

```
BUFFALO INC. LinkStation series HS-DHGL(JINMU)  
HS-DHGLCA1 login: root  
root@HS-DHGLCA1:~#
```

[技術資料](#), [NAS](#), [HS-DHGL](#), [メモ](#)

From:  
<https://wiki.hgotoh.jp/> - 努力したWiki

Permanent link:  
<https://wiki.hgotoh.jp/documents/other/memo01/other-003>

Last update: **2025/11/20 09:14**

